

libusb-1.0.dll Replacement Procedure

Replace libusb-1.0.dll in the installation folder of SONY's Imaging Edge application with the DLL file in libusb-1.0(UDS04022020).zip archive as following procedure.

< Steps >


- ① End Imaging Edge Desktop application if it's running.
- ② Backup original libusb-1.0.dll by changing its filename (ex. libusb-1.0.dll.org)

Note: Please retry to change the filename after restarting your PC if the first attempt to change the file name fails.

- Default Installation Path :
 - C:¥Program Files¥Sony¥Imaging Edge¥LjAdapter
 - If you install the application in a different folder, please locate the file accordingly.

- ③ Download libusb-1.0(UDS04022020).zip and extract the archive.

Copy libusb-1.0.dll in the extracted folder to the Path above.



Reverting libusb-1.0.dll

Revert libusb-1.0.dll to the original DLL file as following procedure when reverting Imaging Edge Remote back

< Procedure >

①End Imaging Edge Desktop application if it's running.

②Delete libusb-1.0.dll that replaced the original libusb-1.0.dll.

Default Installation Path is as below. If it cannot be deleted, please retry after restarting Windows.

- Path : C:\Program Files\Sony\Imaging Edge\LjAdapter
- If you install the application in a different folder, please locate the file accordingly.

③Revert the original libusb-1.0.dll filename. (In the example in the previous page, rename the file from libusb-1.0.dll.org to libusb-1.0.dll.)